

Update guide with MS Windows Software

for the CC 9060, CC 9056, CV 9040 and AD9060

You need to have the following for the update:

-
- A notebook with an integrated Bluetooth module or Bluetooth USB stick
- A Windows XP Service Pack 2 or higher, Windows Vista or 7 with administrator rights
- BURY Update Manager (either from our homepage or your DVD)
- The latest software version for the CC 9060 (e.g. V214 from our homepage)

The update is completed at your own risk! No liability is assumed for possible damage that may occur to the device during the update.

During the update, the supply of power to the system must not be interrupted under any circumstances!

Step 1

Preparation of the update to the CC 9060:

Please carry out the following steps on the CC 9060 in order to prepare the system for the update:






The CC 9060 is now awaiting connection to the PC via Bluetooth in order to receive the update.

Schritt 2


To create the Bluetooth connection to the system:

Please now carry out the following steps on the PC to transfer the update to the hands-free car kit via Bluetooth (in this example, Windows XP):


Open the Windows control panel and select 'Bluetooth devices':



In the next window, please select 'add':




In the next step, please select the tick mark as illustrated, and then click on 'next'




The search for Bluetooth devices then starts:



The CC 9060 should be found with a modem symbol and then displayed. Click on the CC 9060 once to highlight it and then select 'next' again in the field below.



In the following step, please highlight 'select your own master key' and enter the key 1234. After this, click on 'next' again.



The CC 9060 should be found with a modem symbol and then displayed. Click on the CC 9060 once to highlight it and then select 'next' again in the field


below.



Schritt 3:

To send updates to the system using the BURY Update Manager:

Please start the BURY Update Manager and follow the following steps (a red circle):





Für den nachfolgenden Schritt benötigen Sie einen Bluetooth-Stick an bzw. ein Bluetooth-Modul in Ihrem Rechner und eine Bluetooth-Verwaltungssoftware. Mehr Informationen zu diesem Thema erhalten Sie in den beiliegenden Dokumenten.

Kurzinformation:

Installieren Sie die Bluetooth® Verwaltungssoftware.

Bitte setzen Sie den Bluetooth® Stick ein bzw. starten Sie das Bluetooth® Modul an Ihrem Rechner. Aktivieren Sie nun den Updatemodus in der Freisprecheinrichtung.

Starten Sie anschließend die Bluetooth® Verwaltungssoftware und suchen Sie nach der Freisprecheinrichtung. Um eine Bluetooth® Verbindung aufzubauen, geben Sie bitte die PIN-Nummer 1234 ein, falls Sie diese nicht geändert haben.

Klicken Sie auf <Weiter> um fortzufahren.



Select the previously downloaded Update V214.





Wählen Sie bitte den COM-Port aus, an dem der Bluetooth-Stick angeschlossen ist.
Prüfen Sie ggfs. die COM-Ports mit dem beiliegenden Zusatzprogramm COM-Search.

1. Start.

2. Verbinden.
3. Geräteerkennung.
4. Entpacken.
5. Übertragung.
6. Trennung.
7. Ende des Updates.

Klicken Sie auf <Weiter> um fortzufahren.



Eine Verbindung mit der Freisprecheinrichtung wird aufgebaut.
Dies kann einige Sekunden dauern.

1. Start.

2. Verbinden.

3. Geräteerkennung.

4. Entpacken.

5. Übertragung.

6. Trennung.

7. Ende des Updates.

www.bury.com

Browse

Download

Zurück

Weiter

Setup

Info

Abbruch



1. Start.

2. Verbinden.

3. Geräteerkennung.

4. Entpacken.

5. Übertragung.

6. Trennung.

7. Ende des Updates.

Informationen über die Freisprecheinrichtung

Product: CC9060

Device Name: CC9060

Software Version: 0174

Device Variant:

Hardware: BL7031

Device Name: CC9060 Display

Software Version: 169

Device Variant:

Hardware: BL7061

www.bury.com

Browse

Download

Zurück

Weiter

Setup

Info

Abbruch



Die Updatedateien werden entpackt. Dies kann einige Minuten dauern.
Bitte warten.

1. Start.
2. Verbinden.
3. Geräteerkennung.
- 4. Entpacken.**
5. Übertragung.
6. Trennung.
7. Ende des Updates.

www.bury.com

Browse

Download

Zurück

Weiter

Setup

Info

Abbruch



Die Updatedateien werden übertragen.
Dies kann einige Minuten dauern.
Bitte warten.

1. Start.
2. Verbinden.
3. Geräteerkennung.
4. Entpacken.
- 5. Übertragung.**
6. Trennung.
7. Ende des Updates.

www.bury.com

Browse

Download


Zurück

Weiter

Setup

Info

Abbruch



It should now be possible to see the following on the CC 9060:



After transferring the data, you should see a message appear in the system's display: 'successful' (see the photo on the left)



After this, the system restarts and the updating of the display is carried out (see the photo on the right)



The update is then complete!